### **Terminal Setup Document**

Category	Task	Checked?
System	Verify Operating System meets PCI requirements (Operating System still supported – Windows Updates).	
Equipment Info	Get make, model, serial numbers for Terminal, Printer, display, scanner, and cash drawers.	
Date and Time	Set correct time/time zone with daylight savings time (if applicable).	
	Select Internet Time tab > check 'Automatically synchronize time with Internet Time Server'.	
	Click Change Date and Time >> Click calendar Settings >> Click Time >> Short Time h:mm tt >> Long Time h:mm:ss tt	
Taskbar Settings (Win 10 & 11)	Right-click the taskbar.	
	Uncheck "Show Task View button".	
	Click "Search" and change to "Hidden".	
	Disable the show cortana button if available	
	Click Settings. Only "Lock the taskbar" should be turned on.	
	Navigate back to System and then to the Notification area. Turn off all icons except for time, network, touchscreen calibration, and keyboard.	
	Press and Hold Taskbar >> Search >> Hidden >> Next click Settings >> Turn on Lock the taskbar - turn all other options off >> navigate to Notification area >> Select Turn system icons on/off >> Select Clock, Network, Touch keyboard only >> Select which icons appear on the taskbar >> Select Touch Studio Daemon and Network only.	



	Unpin every other taskbar pins except for tonic and Chrome from taskbar	
Windows Personalization	"Background" change to a Solid Color (Navy Blue).	
	"Lock screen" turn off show lock screen.	
	"Start" Turn all off.	
	Settings >> Personalization >> Lock Screen >> Background >> Change background to solid color >> Choose Lock screen >> Background >> Turn off Show lock screen background picture on the sign-in screen >> Select Start >> Turn all options off.	
Windows System Settings	"Notifications" turn off Get notifications from apps and other senders, and any other check boxes selected on this screen	
	"Multitasking" turn off.	
	Settings >> System >> Notifications and actions >> Turn all off except Network (choose Add or remove quick actions).	
Devices and Printers	Select printers & Scanners Click "Add Printer".	
	Select The Printer I Want Isn't listed	
	Select "Local Printer With manual settings" using LPT1.	
	For the driver, select Generic -> "Generic/Text only".	
	Select Do Not Share this printer	
	Check (leave Generic/Text only name), don't test and click finish.	
	Make sure Generic Text is the default printer.	



Devices and Printers >> Control Panel >> Devices and Printers >> Add Printer >> Click Printer that I want isn't listed >> Add local printer or network printer with manual settings >> Use existing port LPT 1 >> Next >> Use Manufacture box >> Scroll to Generic >> In the Right Printers box select Generic Text Only >> Next >> Enter Generic / Text Only as printer name >> Next Select share this printer >> Next >> Do not print the test page >> Select Finish >> Press and Hold Generic / Text printer option >>	
Windows 10 – Settings in the Start Menu, click System > Display > set the resolution to the highest available.	
Settings >> System >> Display >> Advance display settings >> Select recommended resolution >>	
Select Network and sharing center select connections, Properties, and uncheck tcp/ip version 6.	
Open up Properties, click Configure, Power Management, and uncheck Allow the Computer to Turn Off This Device To Save Power.	
Install Google Chrome.	
Add Chrome as default browser	
Setup <u>www.tonicpos.com</u> as the default page.	
Pin Chrome to the taskbar.	
Navigate to Secure.tonicpos.com/public and download the most up to date tonic EXE and install	
(skip this step for KVD,KDS)Set screensaver to "Photos" with 10 minutes as the wait before the screensaver shows.	
Uncheck 'On Resume, password'.	
Change Plan Settings.	
"Put Comp to sleep" to Never.	
"Turn off display" to Never.	
	Printer >> Click Printer that I want isn't listed >> Add local printer or network printer with manual settings >> Use existing port LPT 1 >> Next >> Use Manufacture box >> Scroll to Generic >> In the Right Printers box select Generic Text Only >> Next >> Enter Generic / Text Only as printer name >> Next Select share this printer >> Next >> Do not print the test page >> Select Finish >> Press and Hold Generic / Text printer option >> Windows 10 – Settings in the Start Menu, click System > Display > set the resolution to the highest available.  Settings >> System >> Display >> Advance display settings >> Select recommended resolution >> Select Network and sharing center select connections , Properties, and uncheck tcp/ip version 6.  Open up Properties, click Configure, Power Management, and uncheck Allow the Computer to Turn Off This Device To Save Power.  Install Google Chrome.  Add Chrome as default browser  Setup www.tonicpos.com as the default page.  Pin Chrome to the taskbar.  Navigate to Secure.tonicpos.com/public and download the most up to date tonic EXE and install  (skip this step for KVD,KDS)Set screensaver to "Photos" with 10 minutes as the wait before the screensaver shows.  Uncheck 'On Resume, password'.  Change Plan Settings.  "Put Comp to sleep" to Never.



	"Dim the display" to Never.	
	Change Advanced Power Settings - Turn Off Hard Disk After - Set to "0/Never".	
	Change power plan to the highest performance option available	
	Choose What Power Buttons Do Under Power Options Select change settings that are currently unavailable, Unselect all	
	Change the following: When I press the power button –"Shut down"; When I press the sleep button – "Do nothing".	
Update and security	Navigate to Windows security, Firewall and network protection,turn off for private and public networks,	
	Allow an app through the firewall, change settings, allow another app, find tonic(ordyx one) under program files 86	
	Virus threat protection, manage settings, add or remove exclusions, add exclusion, folder, C drive, Program files 86, tonic (ordyx one), then add another exclusion, c drive, Users, Tonic(ordyx one)	
Programs and Features	Disable or Remove any non TonicPOS remote access software (i.e., VNC, LogMeIn, TeamViewer) as well as any anti-virus (i.e., Norton).	
System	For Computer name enter "(Store #)-TS1" example 0999-TS1 (0999 being the store number).	
	Choose Restart Later	
User Accounts	Delete all admin accounts except 1.	
	Disable Guest Account.	
Windows Updates	Settings > Windows Update: Install all Microsoft updates.	
	Enable automatic updates.	
	Adjust business hours accordingly for updates download/Restart.	



